



Nymi Connect for Windows Release Notes

NCW 1.1.0

2026 May 4, 2026
Version 1

Contents

Contents.....	2
Nymi Connect for Windows 1.1.0.....	3
New In This Release	4
Compatibility.....	4
Known Issues and Limitations.....	5

Table 1: Revision History

Version	Date	Revision History
1	2026 May 4, 2026	First release of document

Nymi Connect for Windows 1.1.0

Nymi Connect for Windows (NCW) aims to simplify and secure this process by enabling the Nymi Band to automatically provide the required credentials when the user taps their band on an NFC or BLE reader, reducing manual input and improving workflow efficiency.

The NCW 1.1.0 is a minor release with Risk Level 0. It can be used for use in production deployments or GxP environments.

Nymi Connect for Windows components

NCW 1.1.0 is a single component release and includes the following component versions:

- Nymi Connect for Windows 1.1.0

Nymi Documentation Package

Documentation has been updated for NCW 1.1.0. For latest documentations visit the Nymi Support site.

- To access all NCW core documents, visit: [Connected Worker Platform Release Documentation](#)

NFC Reader Support

NFC readers were not explicitly tested under the present release. For a list of NFC readers supported in this release, please refer to the [Supported NFC Readers](#) document.

New In This Release

Nymi Connect for Windows and Browser Applications

Nymi Connect for Windows now supports native Windows applications and web applications, with compatibility for both Nymi Band 3 and Nymi Band 4.

Central Audit Logging

This release introduces centralized application logging that captures all significant system events and errors, helping organizations meet auditing and compliance requirements.

Compatibility

Compatibility

NCW 1.1.0 is compatible with CWP 1.20.1 and above.

Known Issues and Limitations

Table 2: Known Issues in NCW 1.1.0

Issue Number	Description
NEM-3763	[NCW] Tool tip showing incorrect error when NCW cannot reach Nymi Agent Workaround: When multiple issues occurs then oldest error is shown instead of newest error regarding network connectivity.
NEM-3772	In Edge, sometimes inject doesn't work, sometime it doesn't Workaround: 1) disable Autofill or 2) Do not move mouse from user name field and Autofill is popped-up
NEM-3738	[NCW] NES URL should not be case sensitive Workaround: for NES URL registry, using proper case sensitive nes service name will not cause any issue.
NEM-3741	[NCW] On init when NBE is not detected, notification says NCW is ready for use Workaround: when user hovers the mouse to NCW icon , User will see correct state of NCW.
NEM-3750	[NCW] User cannot zip up NCW client and NCS log folders Workaround: to collect logs manually selecting all files and place them to reachable location if needed.



Copyright © 2026
Nymi Inc. All rights reserved.
Published in April 2026

Nymi Inc. (Nymi) believes the information in this document is accurate as of its publication date. The information is subject to change without notice.

The information in this document is provided as-is and Nymi makes no representations or warranties of any kind. This document does not provide you with any legal rights to any intellectual property in any Nymi product. You may copy and use this document for your referential purposes.

This software or hardware is developed for general use in a variety of industries and Nymi assumes no liability as a result of their use or application. Nymi, Nymi Band, and other trademarks are the property of Nymi Inc. Other trademarks may be the property of their respective owners.

Published in Canada.
Nymi Inc.
Toronto, Ontario
www.nymi.com